





### Step 3 - Things To Do First

If the SMART Software is installed on a computer where a SMART interactive product is not connected, the computer will begin to look for a SMART interactive product immediately after the software install.

The Following will appear:




Check the **Box** on,  
and the Click **No**.



### Step 3 - Things To Do First

Additionally, after the software has installed, a 'SMART Product Update' application will activate.



It is recommended that this feature be turned off. **Un-Check** the Box.

For updating the software, it is recommended that this process (*Downloading the newest version of the software directly from SMART's Website, and installing*) be repeated.

Additionally, Installing the Gallery and the Lesson Activity Toolkit would not need to be repeated, if you are updating the software on a computer that already has SMART Notebook™.

### Step 3 - Things To Do First





Click on the **"SMART Board Tools"** icon.  
Click on **"Hide Floating Tools"**.



This will *Hide* the **"Floating Tools"**.

It should not appear again unless it is re-activated.


**To re-activate the "Floating Tools"**  
Click on the **"SMART Board Tools"** icon and where it once had **"Hide Floating Tools"** will now have **"Show Floating Tools"**





### Step 3 - Things To Do First

If this is the first time SMART Notebook™ is installed on the computer, you will need **Activation Code (Product Key)**. The following window will appear.



This will be asked for every time SMART Notebook™ is accessed until the **Product Key** is entered.

You will have 30 Days to activate the software by entering the **Product Key**. After 30 days, SMART Notebook™ will not function until a **Product Key** is entered.

*Please note:*

*All the current downloads available for SMART Notebook™ Software Version 11 are classified as a 30-Day Trial Version. In order to release the Trial Version Status, the end user must input an Activation Code. This Activation Code will most likely come from your District's Technology Administrator.*

*If you and/or your District's Technology Administrator are unaware as to how to obtain an activation code, feel free to contact Bret Gensburg ([bret@eagleleti.com](mailto:bret@eagleleti.com)) directly for more information.*


### Step 3 - Things To Do First

The first time, SMART Notebook™ is opened, a 'Tutorial' will appear.


So, Open SMART Notebook™, then close it at least once.

The 'Tutorial' will no longer automatically start when SMART Notebook™ is accessed.

{Although this may not happen for you, the 'Tutorial' automatically starting has been observed per the user account of the computer. Meaning, you log in to the computer, open and close SMART Notebook™ to stop the 'Tutorial' from opening. Another user logs in to the same computer, opens SMART Notebook™ (for the first time) and the "Tutorial" will appear for them.}




If you ever wish to see the 'Tutorial' again, it can be accessed by clicking on the **"Help"** menu.





### Step 3 - Things To Do First

Check the "Gallery" for the proper amount of content.  
Click on the **"Gallery Tab"**.




There should be at least 6705 Items  
in the  
**"Gallery Essentials"**.

There should be at least 760 Items  
in the  
**"Lesson Activity Toolkit 2.0"**.

### Step 3 - Things To Do First

If the "Gallery" is not up-to-date, it is easily fixed by using the **"Show Additional Gallery Actions"** icon.



Be sure to run both **"Updates..."** if needed.